pyOpenSSL Documentation

Release 19.1.0

The pyOpenSSL developers

Contents

1	Contents:					
	1.1	Introduction	3			
	1.2	Installation				
	1.3	OpenSSL — Python interface to OpenSSL	6			
	1.4	Internals				
	1.5	Meta	41			
2 Indices and tables						
Рy	Python Module Index					
In	dex		53			

Release v19.1.0 (What's new?).

pyOpenSSL is a rather thin wrapper around (a subset of) the OpenSSL library. With thin wrapper we mean that a lot of the object methods do nothing more than calling a corresponding function in the OpenSSL library.

Contents 1

2 Contents

CHAPTER 1

Contents:

1.1 Introduction

1.1.1 History

pyOpenSSL was originally created by Martin Sjögren because the SSL support in the standard library in Python 2.1 (the contemporary version of Python when the pyOpenSSL project was begun) was severely limited. Other OpenSSL wrappers for Python at the time were also limited, though in different ways.

Later it was maintained by Jean-Paul Calderone who among other things managed to make pyOpenSSL a pure Python project which the current maintainers are *very* grateful for.

Over the time the standard library's ssl module improved, never reaching the completeness of pyOpenSSL's API coverage. Despite PEP 466 many useful features remain Python 3-only and pyOpenSSL remains the only alternative for full-featured TLS code across all noteworthy Python versions from 2.7 through 3.5 and PyPy.

1.1.2 Development

pyOpenSSL is collaboratively developed by the Python Cryptography Authority (PyCA) that also maintains the low-level bindings called cryptography.

Current maintainer and release manager is Hynek Schlawack.

1.1.3 Contributing

First of all, thank you for your interest in contributing to pyOpenSSL! This project has no company backing its development therefore we're dependent on help by the community.

Filing bug reports

Bug reports are very welcome. Please file them on the GitHub issue tracker. Good bug reports come with extensive descriptions of the error and how to reproduce it. Reporters are strongly encouraged to include an short, self contained, correct example.

Patches

All patches to pyOpenSSL should be submitted in the form of pull requests to the main pyOpenSSL repository, pyca/pyopenssl. These pull requests should satisfy the following properties:

Code

- The pull request should focus on one particular improvement to pyOpenSSL. Create different pull requests for unrelated features or bugfixes.
- Code should follow PEP 8, especially in the "do what code around you does" sense. Follow OpenSSL naming for callables whenever possible is preferred.
- Pull requests that introduce code must test all new behavior they introduce as well as for previously untested or poorly tested behavior that they touch.
- Pull requests are not allowed to break existing tests. We usually don't comment on pull requests that are breaking the CI because we consider them work in progress. Please note that not having 100% code coverage for the code you wrote/touched also causes our CI to fail.

Documentation

When introducing new functionality, please remember to write documentation.

• New functions and methods should have a docstring describing what they do, what parameters they takes, what types those parameters are, and what they return.

Don't forget to add an .. auto (function|class|method):: statement to the relevant API document found in doc/api/ to actually add your function to the Sphinx documentation.

- Do *not* use :py: prefixes when cross-linking (Python is default). Do *not* use the generic :data: or :obj:. Instead use more specific types like :class:,:func: or :meth: if applicable.
- Pull requests that introduce features or fix bugs should note those changes in the CHANGELOG.rst file. Please add new entries to the *top* of the *current* Changes section followed by a line linking to the relevant pull request:

```
- Added ``OpenSSL.crypto.some_func()`` to do something awesome.
[`#1 <https://github.com/pyca/pyopenssl/pull/1>`_]
```

• Use semantic newlines in reStructuredText files (files ending in .rst).

Review

Finally, pull requests must be reviewed before merging. This process mirrors the cryptography code review process. Everyone can perform reviews; this is a very valuable way to contribute, and is highly encouraged.

Pull requests are merged by members of PyCA. They should, of course, keep all the requirements detailed in this document as well as the pyca/cryptography merge requirements in mind.

The final responsibility for the reviewing of merged code lies with the person merging it. Since pyOpenSSL is a sensitive project from a security perspective, reviewers are strongly encouraged to take this review and merge process very seriously.

Finding Help

If you need any help with the contribution process, you'll find us hanging out at #cryptography-dev on Freenode IRC. You can also ask questions on our mailing list.

Please note that this project is released with a Contributor Code of Conduct. By participating in this project you agree to abide by its terms.

Security

If you feel that you found a security-relevant bug that you would prefer to discuss in private, please send us a GPG-encrypted e-mail.

The maintainer can be reached at hs@ox.cx and his GPG key ID is 0xAE2536227F69F181 (Fingerprint: C2A0 4F86 ACE2 8ADC F817 DBB7 AE25 3622 7F69 F181). Feel free to cross-check this information with Keybase.

1.2 Installation

To install pyOpenSSL:

```
$ pip install pyopenssl
```

If you are installing in order to develop on pyOpenSSL, move to the root directory of a pyOpenSSL checkout, and run:

```
$ pip install -e .
```

Warning: As of 0.14, pyOpenSSL is a pure-Python project. That means that if you encounter *any* kind of compiler errors, pyOpenSSL's bugtracker is the **wrong** place to report them because we *cannot* help you.

Please take the time to read the errors and report them/ask help from the appropriate project. The most likely culprit being cryptography that contains OpenSSL's library bindings.

1.2. Installation 5

1.2.1 Supported OpenSSL Versions

pyOpenSSL supports the same platforms and releases as the upstream cryptography project does. Currently that means:

- 1.0.1
- 1.0.2
- 1.1.0
- 1.1.1

You can always find out the versions of pyOpenSSL, cryptography, and the linked OpenSSL by running python -m OpenSSL.debug.

1.2.2 Documentation

The documentation is written in reStructuredText and built using Sphinx:

```
$ cd doc
$ make html
```

1.3 OpenSSL — Python interface to OpenSSL

This package provides a high-level interface to the functions in the OpenSSL library. The following modules are defined:

1.3.1 crypto — Generic cryptographic module

Note: pyca/cryptography is likely a better choice than using this module. It contains a complete set of cryptographic primitives as well as a significantly better and more powerful X509 API. If necessary you can convert to and from cryptography objects using the to_cryptography and from_cryptography methods on X509, X509Req, CRL, and PKey.

Elliptic curves

```
OpenSSL.crypto.get_elliptic_curves()
```

Return a set of objects representing the elliptic curves supported in the OpenSSL build in use.

The curve objects have a unicode name attribute by which they identify themselves.

The curve objects are useful as values for the argument accepted by Context.set_tmp_ecdh() to specify which elliptical curve should be used for ECDHE key exchange.

```
OpenSSL.crypto.get_elliptic_curve(name)
```

Return a single curve object selected by name.

See get_elliptic_curves() for information about curve objects.

Parameters name (unicode) - The OpenSSL short name identifying the curve object to retrieve.

If the named curve is not supported then ValueError is raised.

Serialization and deserialization

The following serialization functions take one of these constants to determine the format.

```
OpenSSL.crypto.FILETYPE_PEM
```

FILETYPE_PEM serializes data to a Base64-encoded encoded representation of the underlying ASN.1 data structure. This representation includes delimiters that define what data structure is contained within the Base64-encoded block: for example, for a certificate, the delimiters are ----BEGIN CERTIFICATE---- and ----END CERTIFICATE----.

```
OpenSSL.crypto.FILETYPE_ASN1
```

FILETYPE_ASN1 serializes data to the underlying ASN.1 data structure. The format used by FILETYPE_ASN1 is also sometimes referred to as DER.

Certificates

```
OpenSSL.crypto.dump_certificate(type, cert)
```

Dump the certificate *cert* into a buffer string encoded with the type *type*.

Parameters

- type The file type (one of FILETYPE_PEM, FILETYPE_ASN1, or FILETYPE_TEXT)
- cert The certificate to dump

Returns The buffer with the dumped certificate in

```
OpenSSL.crypto.load_certificate(type, buffer)
```

Load a certificate (X509) from the string *buffer* encoded with the type *type*.

Parameters

- type The file type (one of FILETYPE_PEM, FILETYPE_ASN1)
- **buffer** (bytes) The buffer the certificate is stored in

Returns The X509 object

Certificate signing requests

```
OpenSSL.crypto.dump_certificate_request(type, req)
```

Dump the certificate request req into a buffer string encoded with the type type.

Parameters

- type The file type (one of FILETYPE_PEM, FILETYPE_ASN1)
- req The certificate request to dump

Returns The buffer with the dumped certificate request in

```
OpenSSL.crypto.load_certificate_request(type, buffer)
```

Load a certificate request (X509Req) from the string buffer encoded with the type type.

Parameters

- type The file type (one of FILETYPE_PEM, FILETYPE_ASN1)
- **buffer** The buffer the certificate request is stored in

Returns The X509Req object

Private keys

OpenSSL.crypto.dump_privatekey(type, pkey, cipher=None, passphrase=None)

Dump the private key *pkey* into a buffer string encoded with the type *type*. Optionally (if *type* is *FILETYPE_PEM*) encrypting it using *cipher* and *passphrase*.

Parameters

- **type** The file type (one of FILETYPE_PEM, FILETYPE_ASN1, or FILETYPE_TEXT)
- pkey (PKey) The PKey to dump
- cipher (optional) if encrypted PEM format, the cipher to use
- passphrase (optional) if encrypted PEM format, this can be either the passphrase to use, or a callback for providing the passphrase.

Returns The buffer with the dumped key in

Return type bytes

OpenSSL.crypto.load_privatekey(type, buffer, passphrase=None)

Load a private key (PKey) from the string *buffer* encoded with the type *type*.

Parameters

- type The file type (one of FILETYPE_PEM, FILETYPE_ASN1)
- buffer The buffer the key is stored in
- **passphrase** (optional) if encrypted PEM format, this can be either the passphrase to use, or a callback for providing the passphrase.

Returns The PKey object

Public keys

OpenSSL.crypto.dump_publickey(type, pkey)

Dump a public key to a buffer.

Parameters

- **type** The file type (one of FILETYPE_PEM or FILETYPE_ASN1).
- **pkey** (PKey) The public key to dump

Returns The buffer with the dumped key in it.

Return type bytes

OpenSSL.crypto.load_publickey(type, buffer)

Load a public key from a buffer.

Parameters

- **type** The file type (one of FILETYPE_PEM, FILETYPE_ASN1).
- buffer (A Python string object, either unicode or bytestring.)

 The buffer the key is stored in.

Returns The PKey object.

Return type PKey

Certificate revocation lists

OpenSSL.crypto.dump_crl(type, crl)

Dump a certificate revocation list to a buffer.

Parameters

- type The file type (one of FILETYPE_PEM, FILETYPE_ASN1, or FILETYPE_TEXT).
- crl (CRL) The CRL to dump.

Returns The buffer with the CRL.

Return type bytes

OpenSSL.crypto.load_crl(type, buffer)

Load Certificate Revocation List (CRL) data from a string buffer. buffer encoded with the type type.

Parameters

- type The file type (one of FILETYPE_PEM, FILETYPE_ASN1)
- buffer The buffer the CRL is stored in

Returns The PKey object

OpenSSL.crypto.load_pkcs7_data(type, buffer)

Load pkcs7 data from the string *buffer* encoded with the type *type*.

Parameters

- type The file type (one of FILETYPE_PEM or FILETYPE_ASN1)
- **buffer** The buffer with the pkcs7 data.

Returns The PKCS7 object

OpenSSL.crypto.load_pkcs12 (buffer, passphrase=None)

Load pkcs12 data from the string *buffer*. If the pkcs12 structure is encrypted, a *passphrase* must be included. The MAC is always checked and thus required.

See also the man page for the C function PKCS12_parse().

Parameters

- buffer The buffer the certificate is stored in
- passphrase (Optional) The password to decrypt the PKCS12 lump

Returns The PKCS12 object

Signing and verifying signatures

OpenSSL.crypto.sign(pkey, data, digest)

Sign a data string using the given key and message digest.

Parameters

- pkey PKey to sign with
- data data to be signed
- digest message digest to use

Returns signature

```
New in version 0.11.
```

OpenSSL.crypto.verify(cert, signature, data, digest)

Verify the signature for a data string.

Parameters

- **cert** signing certificate (X509 object) corresponding to the private key which generated the signature.
- **signature** signature returned by sign function
- data data to be verified
- digest message digest to use

Returns None if the signature is correct, raise exception otherwise.

New in version 0.11.

X509 objects

```
class OpenSSL.crypto.X509
```

An X.509 certificate.

add_extensions (extensions)

Add extensions to the certificate.

Parameters extensions (An iterable of X509Extension objects.) – The extensions to add.

Returns None

```
digest (digest_name)
```

Return the digest of the X509 object.

Parameters digest_name (bytes) - The name of the digest algorithm to use.

Returns The digest of the object, formatted as b": "-delimited hex pairs.

Return type bytes

classmethod from_cryptography(crypto_cert)

Construct based on a cryptography crypto_cert.

Parameters crypto_key (cryptography.x509.Certificate) - A cryptography X.509 certificate.

Return type X509

New in version 17.1.0.

$get_extension(index)$

Get a specific extension of the certificate by index.

Extensions on a certificate are kept in order. The index parameter selects which extension will be returned.

Parameters index (int) – The index of the extension to retrieve.

Returns The extension at the specified index.

Return type X509Extension

Raises IndexError – If the extension index was out of bounds.

New in version 0.12.

get_extension_count()

Get the number of extensions on this certificate.

Returns The number of extensions.

```
Return type int
```

New in version 0.12.

get_issuer()

Return the issuer of this certificate.

This creates a new X509Name that wraps the underlying issuer name field on the certificate. Modifying it will modify the underlying certificate, and will have the effect of modifying any other X509Name that refers to this issuer.

Returns The issuer of this certificate.

Return type X509Name

get_notAfter()

Get the timestamp at which the certificate stops being valid.

The timestamp is formatted as an ASN.1 TIME:

```
YYYYMMDDhhmmssZ
```

Returns A timestamp string, or None if there is none.

Return type bytes or NoneType

get_notBefore()

Get the timestamp at which the certificate starts being valid.

The timestamp is formatted as an ASN.1 TIME:

```
YYYYMMDDhhmmssZ
```

Returns A timestamp string, or None if there is none.

Return type bytes or NoneType

get_pubkey()

Get the public key of the certificate.

Returns The public key.

Return type *PKey*

get_serial_number()

Return the serial number of this certificate.

Returns The serial number.

Return type int

get_signature_algorithm()

Return the signature algorithm used in the certificate.

Returns The name of the algorithm.

Return type bytes

Raises ValueError – If the signature algorithm is undefined.

New in version 0.13.

get_subject()

Return the subject of this certificate.

This creates a new X509Name that wraps the underlying subject name field on the certificate. Modifying it will modify the underlying certificate, and will have the effect of modifying any other X509Name that refers to this subject.

Returns The subject of this certificate.

Return type X509Name

get_version()

Return the version number of the certificate.

Returns The version number of the certificate.

Return type int

gmtime_adj_notAfter(amount)

Adjust the time stamp on which the certificate stops being valid.

Parameters amount (*int*) – The number of seconds by which to adjust the timestamp.

Returns None

gmtime_adj_notBefore(amount)

Adjust the timestamp on which the certificate starts being valid.

Parameters amount – The number of seconds by which to adjust the timestamp.

Returns None

has_expired()

Check whether the certificate has expired.

Returns True if the certificate has expired, False otherwise.

Return type bool

set_issuer(issuer)

Set the issuer of this certificate.

Parameters issuer (X509Name) – The issuer.

Returns None

set_notAfter(when)

Set the timestamp at which the certificate stops being valid.

The timestamp is formatted as an ASN.1 TIME:

YYYYMMDDhhmmssZ

Parameters when (bytes) – A timestamp string.

Returns None

set_notBefore(when)

Set the timestamp at which the certificate starts being valid.

The timestamp is formatted as an ASN.1 TIME:

```
YYYYMMDDhhmmssZ
```

Parameters when (bytes) – A timestamp string.

Returns None

set_pubkey (pkey)

Set the public key of the certificate.

Parameters pkey (PKey) – The public key.

Returns None

set_serial_number(serial)

Set the serial number of the certificate.

Parameters serial (int) – The new serial number.

Returns :py:data'None'

set subject(subject)

Set the subject of this certificate.

Parameters subject (X509Name) – The subject.

Returns None

set version(version)

Set the version number of the certificate. Note that the version value is zero-based, eg. a value of 0 is V1.

Parameters version (int) – The version number of the certificate.

Returns None

sign (pkey, digest)

Sign the certificate with this key and digest type.

Parameters

- **pkey** (*PKey*) The key to sign with.
- **digest** (bytes) The name of the message digest to use.

Returns None

subject_name_hash()

Return the hash of the X509 subject.

Returns The hash of the subject.

Return type bytes

to_cryptography()

Export as a cryptography certificate.

Return type cryptography.x509.Certificate

New in version 17.1.0.

X509Name objects

class OpenSSL.crypto.X509Name (name)

An X.509 Distinguished Name.

Variables

- **countryName** The country of the entity.
- C Alias for countryName.
- **stateOrProvinceName** The state or province of the entity.
- ST Alias for stateOrProvinceName.
- localityName The locality of the entity.
- L Alias for localityName.
- organizationName The organization name of the entity.
- O Alias for organizationName.
- organizationalUnitName The organizational unit of the entity.
- OU Alias for organizationalUnitName
- **commonName** The common name of the entity.
- CN Alias for commonName.
- **emailAddress** The e-mail address of the entity.

```
___init___(name)
```

Create a new X509Name, copying the given X509Name instance.

Parameters name (X509Name) – The name to copy.

```
__setattr__(name, value)
x.__setattr__('name', value) <==> x.name = value
```

der()

Return the DER encoding of this name.

Returns The DER encoded form of this name.

```
Return type bytes
```

```
get_components()
```

Returns the components of this name, as a sequence of 2-tuples.

Returns The components of this name.

Return type list of name, value tuples.

hash()

Return an integer representation of the first four bytes of the MD5 digest of the DER representation of the name.

This is the Python equivalent of OpenSSL's X509_NAME_hash.

Returns The (integer) hash of this name.

Return type int

X509Req objects

add extensions(extensions)

Add extensions to the certificate signing request.

Parameters extensions (iterable of X509Extension) – The X.509 extensions to add.

Returns None

classmethod from_cryptography(crypto_req)

Construct based on a cryptography crypto_req.

Parameters crypto_req (cryptography.x509.CertificateSigningRequest)

- A cryptography X.509 certificate signing request

Return type X509Req

New in version 17.1.0.

get extensions()

Get X.509 extensions in the certificate signing request.

Returns The X.509 extensions in this request.

Return type list of X509Extension objects.

New in version 0.15.

get_pubkey()

Get the public key of the certificate signing request.

Returns The public key.

Return type *PKey*

get_subject()

Return the subject of this certificate signing request.

This creates a new X509Name that wraps the underlying subject name field on the certificate signing request. Modifying it will modify the underlying signing request, and will have the effect of modifying any other X509Name that refers to this subject.

Returns The subject of this certificate signing request.

Return type X509Name

get_version()

Get the version subfield (RFC 2459, section 4.1.2.1) of the certificate request.

Returns The value of the version subfield.

Return type int

set pubkey (pkey)

Set the public key of the certificate signing request.

Parameters pkey (*PKey*) – The public key to use.

Returns None

set version(version)

Set the version subfield (RFC 2459, section 4.1.2.1) of the certificate request.

Parameters version (*int*) – The version number.

Returns None

sign (pkey, digest)

Sign the certificate signing request with this key and digest type.

Parameters

- **pkey** (*PKey*) The key pair to sign with.
- **digest** (bytes) The name of the message digest to use for the signature, e.g. b"sha256".

Returns None

to_cryptography()

Export as a cryptography certificate signing request.

Return type cryptography.x509.CertificateSigningRequest

New in version 17.1.0.

verify(pkey)

Verifies the signature on this certificate signing request.

Parameters key (PKey) – A public key.

Returns True if the signature is correct.

Return type bool

Raises *OpenSSL. crypto. Error* – If the signature is invalid or there is a problem verifying the signature.

X509Store objects

class OpenSSL.crypto.X509Store

An X.509 store.

An X.509 store is used to describe a context in which to verify a certificate. A description of a context may include a set of certificates to trust, a set of certificate revocation lists, verification flags and more.

An X.509 store, being only a description, cannot be used by itself to verify a certificate. To carry out the actual verification process, see X509StoreContext.

add_cert (cert)

Adds a trusted certificate to this store.

Adding a certificate with this method adds this certificate as a trusted certificate.

Parameters cert (X509) – The certificate to add to this store.

Raises

- **TypeError** If the certificate is not an *X509*.
- OpenSSL. crypto. Error If OpenSSL was unhappy with your certificate.

Returns None if the certificate was added successfully.

add crl(crl)

Add a certificate revocation list to this store.

The certificate revocation lists added to a store will only be used if the associated flags are configured to check certificate revocation lists.

New in version 16.1.0.

Parameters crl (CRL) – The certificate revocation list to add to this store.

Returns None if the certificate revocation list was added successfully.

set_flags (flags)

Set verification flags to this store.

Verification flags can be combined by oring them together.

Note: Setting a verification flag sometimes requires clients to add additional information to the store, otherwise a suitable error will be raised.

For example, in setting flags to enable CRL checking a suitable CRL must be added to the store otherwise an error will be raised.

New in version 16.1.0.

Parameters flags (int) – The verification flags to set on this store. See X509StoreFlags for available constants.

Returns None if the verification flags were successfully set.

set_time (vfy_time)

Set the time against which the certificates are verified.

Normally the current time is used.

Note: For example, you can determine if a certificate was valid at a given time.

New in version 17.0.0.

Parameters vfy_time (datetime) – The verification time to set on this store.

Returns None if the verification time was successfully set.

X509StoreContextError objects

class OpenSSL.crypto.X509StoreContextError (message, certificate)

An exception raised when an error occurred while verifying a certificate using *OpenSSL.X509StoreContext.verify_certificate*.

Variables certificate - The certificate which caused verificate failure.

X509StoreContext objects

class OpenSSL.crypto.X509StoreContext(store, certificate)

An X.509 store context.

An X.509 store context is used to carry out the actual verification process of a certificate in a described context. For describing such a context, see *X509Store*.

Variables

- _store_ctx The underlying X509_STORE_CTX structure used by this instance. It is dynamically allocated and automatically garbage collected.
- _store See the store __init__ parameter.
- _cert See the certificate __init__ parameter.

Parameters

- store (X509Store) The certificates which will be trusted for the purposes of any verifications.
- **certificate** (X509) The certificate to be verified.

```
set_store(store)
```

Set the context's X.509 store.

New in version 0.15.

Parameters store (X509Store) – The store description which will be used for the purposes of any *future* verifications.

verify_certificate()

Verify a certificate in a context.

New in version 0.15.

Raises *X509StoreContextError* – If an error occurred when validating a certificate in the context. Sets certificate attribute to indicate which certificate caused the error.

X509StoreFlags constants

```
class OpenSSL.crypto.X509StoreFlags
```

Flags for X509 verification, used to change the behavior of X509Store.

See OpenSSL Verification Flags for details.

CRL_CHECK

CRL_CHECK_ALL

IGNORE_CRITICAL

X509 STRICT

ALLOW_PROXY_CERTS

POLICY_CHECK

EXPLICIT_POLICY

INHIBIT_MAP

NOTIFY_POLICY

CHECK_SS_SIGNATURE

CB_ISSUER_CHECK

PKey objects

```
class OpenSSL.crypto.PKey
```

A class representing an DSA or RSA public key or key pair.

bits()

Returns the number of bits of the key

Returns The number of bits of the key.

check()

Check the consistency of an RSA private key.

This is the Python equivalent of OpenSSL's RSA_check_key.

Returns True if key is consistent.

Raises

- OpenSSL.crypto.Error if the key is inconsistent.
- **TypeError** if the key is of a type which cannot be checked. Only RSA keys can currently be checked.

classmethod from_cryptography_key(crypto_key)

Construct based on a cryptography crypto_key.

Parameters crypto_key (One of cryptography's key interfaces.) - A cryptography key.

Return type PKey

New in version 16.1.0.

generate_key (type, bits)

Generate a key pair of the given type, with the given number of bits.

This generates a key "into" the this object.

Parameters

- **type** (*TYPE_RSA* or *TYPE_DSA*) The key type.
- bits (int >= 0) The number of bits.

Raises

- **TypeError** If type or bits isn't of the appropriate type.
- **ValueError** If the number of bits isn't an integer of the appropriate size.

Returns None

to_cryptography_key()

Export as a cryptography key.

Return type One of cryptography's key interfaces.

New in version 16.1.0.

type()

Returns the type of the key

Returns The type of the key.

```
OpenSSL.crypto.TYPE_RSA
OpenSSL.crypto.TYPE_DSA
```

Key type constants.

PKCS7 objects

PKCS7 objects have the following methods:

```
class OpenSSL.crypto.PKCS7
```

```
get_type_name()
```

Returns the type name of the PKCS7 structure

Returns A string with the typename

```
type_is_data()
          Check if this NID_pkcs7_data object
              Returns True if the PKCS7 is of type data
     type_is_enveloped()
          Check if this NID_pkcs7_enveloped object
              Returns True if the PKCS7 is of type enveloped
     type_is_signed()
          Check if this NID_pkcs7_signed object
              Returns True if the PKCS7 is of type signed
     type_is_signedAndEnveloped()
          Check if this NID_pkcs7_signedAndEnveloped object
              Returns True if the PKCS7 is of type signedAndEnveloped
PKCS12 objects
class OpenSSL.crypto.PKCS12
     A PKCS #12 archive.
     export (passphrase=None, iter=2048, maciter=1)
          Dump a PKCS12 object as a string.
          For more information, see the PKCS12_create() man page.
              Parameters
                  • passphrase (bytes) - The passphrase used to encrypt the structure. Unlike some
                    other passphrase arguments, this must be a string, not a callback.
                  • iter (int) – Number of times to repeat the encryption step.
                  • maciter (int) - Number of times to repeat the MAC step.
              Returns The string representation of the PKCS #12 structure.
              Return type
     get_ca_certificates()
          Get the CA certificates in the PKCS #12 structure.
              Returns A tuple with the CA certificates in the chain, or None if there are none.
              Return type tuple of X509 or None
     get_certificate()
          Get the certificate in the PKCS #12 structure.
              Returns The certificate, or None if there is none.
              Return type X509 or None
     get_friendlyname()
          Get the friendly name in the PKCS# 12 structure.
              Returns The friendly name, or None if there is none.
              Return type bytes or None
     get_privatekey()
```

Get the private key in the PKCS #12 structure.

Returns The private key, or None if there is none.

Return type PKey

set_ca_certificates(cacerts)

Replace or set the CA certificates within the PKCS12 object.

Parameters cacerts (An iterable of *X509* or None) – The new CA certificates, or None to unset them.

Returns None

set_certificate(cert)

Set the certificate in the PKCS #12 structure.

Parameters cert (X509 or None) – The new certificate, or None to unset it.

Returns None

set_friendlyname (name)

Set the friendly name in the PKCS #12 structure.

Parameters name (bytes or None) - The new friendly name, or None to unset.

Returns None

set_privatekey(pkey)

Set the certificate portion of the PKCS #12 structure.

Parameters pkey (PKey or None) – The new private key, or None to unset it.

Returns None

X509Extension objects

```
class OpenSSL.crypto.X509Extension (type_name, critical, value, subject=None, issuer=None)
An X.509 v3 certificate extension.
```

__init__(type_name, critical, value, subject=None, issuer=None)
Initializes an X509 extension.

Parameters

- type_name (bytes) The name of the type of extension to create.
- **critical** (bool) A flag indicating whether this is a critical extension.
- value (bytes) The value of the extension.
- **subject** (*X*509) Optional X509 certificate to use as subject.
- **issuer** (*X*509) Optional X509 certificate to use as issuer.

__str__()

Returns a nice text representation of the extension

get_critical()

Returns the critical field of this X.509 extension.

Returns The critical field.

get_data()

Returns the data of the X509 extension, encoded as ASN.1.

Returns The ASN.1 encoded data of this X509 extension.

```
Return type bytes
          New in version 0.12.
     get_short_name()
          Returns the short type name of this X.509 extension.
          The result is a byte string such as b"basicConstraints".
               Returns The short type name.
               Return type bytes
          New in version 0.12.
NetscapeSPKI objects
class OpenSSL.crypto.NetscapeSPKI
     A Netscape SPKI object.
     ___init___()
          x__init__(...) initializes x; see help(type(x)) for signature
     b64_encode()
          Generate a base64 encoded representation of this SPKI object.
               Returns The base64 encoded string.
               Return type bytes
     get_pubkey()
          Get the public key of this certificate.
               Returns The public key.
               Return type PKey
     set_pubkey (pkey)
          Set the public key of the certificate
               Parameters pkey - The public key
               Returns None
     sign (pkey, digest)
          Sign the certificate request with this key and digest type.
               Parameters
                   • pkey (PKey) – The private key to sign with.
                   • digest (bytes) - The message digest to use.
               Returns None
     verify(key)
          Verifies a signature on a certificate request.
               Parameters key (PKey) – The public key that signature is supposedly from.
               Returns True if the signature is correct.
               Return type bool
               Raises OpenSSL.crypto.Error - If the signature is invalid, or there was a problem veri-
                   fying the signature.
```

CRL objects

```
class OpenSSL.crypto.CRL
     A certificate revocation list.
     ___init___()
          x__init__(...) initializes x; see help(type(x)) for signature
     add_revoked (revoked)
          Add a revoked (by value not reference) to the CRL structure
          This revocation will be added by value, not by reference. That means it's okay to mutate it after adding: it
          won't affect this CRL.
              Parameters revoked (Revoked) – The new revocation.
              Returns None
     export (cert, key, type=1, days=100, digest=<object object>)
          Export the CRL as a string.
              Parameters
                   • cert (X509) – The certificate used to sign the CRL.
                   • key (PKey) – The key used to sign the CRL.
                   • type (int) - The export format, either FILETYPE_PEM, FILETYPE_ASN1, or
                    FILETYPE_TEXT.
                   • days (int) – The number of days until the next update of this CRL.
                   • digest (bytes) – The name of the message digest to use (eg b"sha256").
              Return type bytes
     classmethod from_cryptography(crypto_crl)
          Construct based on a cryptography crypto crl.
              Parameters crypto_crl (cryptography.x509.CertificateRevocationList)
                  - A cryptography certificate revocation list
              Return type CRL
          New in version 17.1.0.
     get_issuer()
          Get the CRL's issuer.
          New in version 16.1.0.
              Return type X509Name
     get_revoked()
          Return the revocations in this certificate revocation list.
          These revocations will be provided by value, not by reference. That means it's okay to mutate them: it
          won't affect this CRL.
```

Returns The revocations in this CRL.

Return type tuple of Revocation

set_lastUpdate(when)

Set when the CRL was last updated.

The timestamp is formatted as an ASN.1 TIME:

YYYYMMDDhhmmssZ

New in version 16.1.0.

Parameters when (bytes) – A timestamp string.

Returns None

set_nextUpdate(when)

Set when the CRL will next be udpated.

The timestamp is formatted as an ASN.1 TIME:

YYYYMMDDhhmmssZ

New in version 16.1.0.

Parameters when (bytes) – A timestamp string.

Returns None

set_version (version)

Set the CRL version.

New in version 16.1.0.

Parameters version (*int*) – The version of the CRL.

Returns None

sign (issuer_cert, issuer_key, digest)

Sign the CRL.

Signing a CRL enables clients to associate the CRL itself with an issuer. Before a CRL is meaningful to other OpenSSL functions, it must be signed by an issuer.

This method implicitly sets the issuer's name based on the issuer certificate and private key used to sign the CRL.

New in version 16.1.0.

Parameters

- issuer_cert (X509) The issuer's certificate.
- issuer_key (PKey) The issuer's private key.
- **digest** (bytes) The digest method to sign the CRL with.

to_cryptography()

Export as a cryptography CRL.

Return type cryptography.x509.CertificateRevocationList

New in version 17.1.0.

Revoked objects

class OpenSSL.crypto.Revoked

A certificate revocation.

```
all reasons()
```

Return a list of all the supported reason strings.

This list is a copy; modifying it does not change the supported reason strings.

```
Returns A list of reason strings.
         Return type list of bytes
get_reason()
     Get the reason of this revocation.
         Returns The reason, or None if there is none.
         Return type bytes or NoneType
     See also:
     all_reasons(), which gives you a list of all supported reasons this method might return.
get_rev_date()
     Get the revocation timestamp.
         Returns The timestamp of the revocation, as ASN.1 TIME.
         Return type bytes
get serial()
     Get the serial number.
     The serial number is formatted as a hexadecimal number encoded in ASCII.
         Returns The serial number.
         Return type bytes
set reason(reason)
     Set the reason of this revocation.
     If reason is None, delete the reason instead.
         Parameters reason (bytes or NoneType) – The reason string.
         Returns None
     See also:
     all_reasons (), which gives you a list of all supported reasons which you might pass to this method.
set rev date (when)
     Set the revocation timestamp.
         Parameters when (bytes) – The timestamp of the revocation, as ASN.1 TIME.
         Returns None
set serial(hex str)
     Set the serial number.
     The serial number is formatted as a hexadecimal number encoded in ASCII.
         Parameters hex_str (bytes) - The new serial number.
         Returns None
```

Exceptions

exception OpenSSL.crypto.Error

Generic exception used in the crypto module.

Digest names

Several of the functions and methods in this module take a digest name. These must be strings describing a digest algorithm supported by OpenSSL (by EVP_get_digestbyname, specifically). For example, b"sha256" or b"sha384".

More information and a list of these digest names can be found in the EVP_DigestInit(3) man page of your OpenSSL installation. This page can be found online for the latest version of OpenSSL: https://www.openssl.org/docs/manmaster/man3/EVP_DigestInit.html

1.3.2 SSL — An interface to the SSL-specific parts of OpenSSL

This module handles things specific to SSL. There are two objects defined: Context, Connection.

```
OpenSSL.SSL.SSLv2_METHOD
OpenSSL.SSL.SSLv3_METHOD
OpenSSL.SSL.SSLv23_METHOD
OpenSSL.SSL.TLSv1_METHOD
OpenSSL.SSL.TLSv1_1_METHOD
OpenSSL.SSL.TLSv1_2_METHOD
```

These constants represent the different SSL methods to use when creating a context object. If the underlying OpenSSL build is missing support for any of these protocols, constructing a *Context* using the corresponding *_METHOD will raise an exception.

```
OpenSSL.SSL.VERIFY_NONE
OpenSSL.SSL.VERIFY_PEER
OpenSSL.SSL.VERIFY_FAIL_IF_NO_PEER_CERT
```

These constants represent the verification mode used by the Context object's set_verify() method.

```
OpenSSL.SSL.FILETYPE_PEM OpenSSL.SSL.FILETYPE_ASN1
```

File type constants used with the use_certificate_file() and use_privatekey_file() methods of Context objects.

```
OpenSSL.SSL.OP_SINGLE_DH_USE
OpenSSL.SSL.OP SINGLE ECDH USE
```

Constants used with set_options () of Context objects.

When these options are used, a new key will always be created when using ephemeral (Elliptic curve) Diffie-Hellman.

```
OpenSSL.SSL.OP_EPHEMERAL_RSA
```

Constant used with set_options() of Context objects.

When this option is used, ephemeral RSA keys will always be used when doing RSA operations.

```
OpenSSL.SSL.OP NO TICKET
```

Constant used with set_options() of Context objects.

When this option is used, the session ticket extension will not be used.

```
OpenSSL.SSL.OP_NO_COMPRESSION
```

Constant used with set_options() of Context objects.

When this option is used, compression will not be used.

```
OpenSSL.SSL.OP_NO_SSLv2
OpenSSL.SSL.OP_NO_SSLv3
OpenSSL.SSL.OP_NO_TLSv1
```

```
OpenSSL.SSL.OP_NO_TLSv1_1
OpenSSL.SSL.OP_NO_TLSv1_2
OpenSSL.SSL.OP NO TLSv1 3
```

Constants used with set_options() of Context objects.

Each of these options disables one version of the SSL/TLS protocol. This is interesting if you're using e.g. SSLv23_METHOD to get an SSLv2-compatible handshake, but don't want to use SSLv2. If the underlying OpenSSL build is missing support for any of these protocols, the OP_NO_* constant may be undefined.

```
OpenSSL.SSL.SSLEAY_VERSION
OpenSSL.SSL.SSLEAY_CFLAGS
OpenSSL.SSL.SSLEAY_BUILT_ON
OpenSSL.SSL.SSLEAY_PLATFORM
OpenSSL.SSL.SSLEAY_DIR
```

Constants used with SSLeay_version() to specify what OpenSSL version information to retrieve. See the man page for the SSLeay_version() C API for details.

```
OpenSSL.SSL.SESS_CACHE_OFF
OpenSSL.SSL.SESS_CACHE_CLIENT
OpenSSL.SSL.SESS_CACHE_SERVER
OpenSSL.SSL.SESS_CACHE_BOTH
OpenSSL.SSL.SESS_CACHE_NO_AUTO_CLEAR
OpenSSL.SSL.SESS_CACHE_NO_INTERNAL_LOOKUP
OpenSSL.SSL.SESS_CACHE_NO_INTERNAL_STORE
OpenSSL.SSL.SESS_CACHE_NO_INTERNAL
```

Constants used with <code>Context.set_session_cache_mode()</code> to specify the behavior of the session cache and potential session reuse. See the man page for the <code>SSL_CTX_set_session_cache_mode()</code> C API for details.

New in version 0.14.

OpenSSL.SSL.OPENSSL_VERSION_NUMBER

An integer giving the version number of the OpenSSL library used to build this version of pyOpenSSL. See the man page for the <code>SSLeay_version()</code> C API for details.

OpenSSL.SSL.NO_OVERLAPPING_PROTOCOLS

A sentinel value that can be returned by the callback passed to Context. $set_alpn_select_callback()$ to indicate that the handshake can continue without a specific application protocol.

New in version 19.1.

```
{\tt OpenSSL.SSL.SSLeay\_version}~(\textit{type})
```

Return a string describing the version of OpenSSL in use.

Parameters type – One of the SSLEAY_ constants defined in this module.

```
OpenSSL.SSL.ContextType
```

See Context.

class OpenSSL.SSL.Context(method)

OpenSSL.SSL.Context instances define the parameters for setting up new SSL connections.

Parameters method – One of SSLv2_METHOD, SSLv3_METHOD, SSLv23_METHOD, or TLSv1_METHOD.

class OpenSSL.SSL.Session

A class representing an SSL session. A session defines certain connection parameters which may be re-used to speed up the setup of subsequent connections.

New in version 0.14.

OpenSSL.SSL.ConnectionType

See Connection.

class OpenSSL.SSL.Connection(context, socket)

A class representing SSL connections.

context should be an instance of Context and socket should be a socket object. socket may be None; in this case, the Connection is created with a memory BIO: see the bio_read(), bio_write(), and bio_shutdown() methods.

exception OpenSSL.SSL.Error

This exception is used as a base class for the other SSL-related exceptions, but may also be raised directly.

Whenever this exception is raised directly, it has a list of error messages from the OpenSSL error queue, where each item is a tuple (*lib*, function, reason). Here *lib*, function and reason are all strings, describing where and what the problem is. See err (3) for more information.

exception OpenSSL.SSL.ZeroReturnError

This exception matches the error return code SSL_ERROR_ZERO_RETURN, and is raised when the SSL Connection has been closed. In SSL 3.0 and TLS 1.0, this only occurs if a closure alert has occurred in the protocol, i.e. the connection has been closed cleanly. Note that this does not necessarily mean that the transport layer (e.g. a socket) has been closed.

It may seem a little strange that this is an exception, but it does match an SSL_ERROR code, and is very convenient.

exception OpenSSL.SSL.WantReadError

The operation did not complete; the same I/O method should be called again later, with the same arguments. Any I/O method can lead to this since new handshakes can occur at any time.

The wanted read is for **dirty** data sent over the network, not the **clean** data inside the tunnel. For a socket based SSL connection, **read** means data coming at us over the network. Until that read succeeds, the attempted <code>OpenSSL.SSL.Connection.recv()</code>, <code>OpenSSL.SSL.Connection.send()</code>, **or** <code>OpenSSL.SSL.Connection.do_handshake()</code> is prevented or incomplete. You probably want to <code>select()</code> on the socket before trying again.

exception OpenSSL.SSL.WantWriteError

See WantReadError. The socket send buffer may be too full to write more data.

exception OpenSSL.SSL.WantX509LookupError

The operation did not complete because an application callback has asked to be called again. The I/O method should be called again later, with the same arguments.

Note: This won't occur in this version, as there are no such callbacks in this version.

exception OpenSSL.SSL.SysCallError

The SysCallError occurs when there's an I/O error and OpenSSL's error queue does not contain any information. This can mean two things: An error in the transport protocol, or an end of file that violates the protocol. The parameter to the exception is always a pair (errnum, errstr).

Context objects

Context objects have the following methods:

¹ Actually, all that is required is an object that **behaves** like a socket, you could even use files, even though it'd be tricky to get the handshakes right!

```
class OpenSSL.SSL.Context (method)
     OpenSSL.SSL.Context instances define the parameters for setting up new SSL connections.
          Parameters method - One of SSLv2_METHOD, SSLv3_METHOD, SSLv23_METHOD, or
              TLSv1 METHOD.
     add_client_ca (certificate_authority)
          Add the CA certificate to the list of preferred signers for this context.
          The list of certificate authorities will be sent to the client when the server requests a client certificate.
              Parameters certificate_authority - certificate authority's X509 certificate.
              Returns None
          New in version 0.10.
     add_extra_chain_cert (certobj)
          Add certificate to chain
              Parameters certobj - The X509 certificate object to add to the chain
              Returns None
     check privatekey()
          Check if the private key (loaded with use_privatekey()) matches the certificate (loaded with
          use_certificate())
              Returns None (raises Error if something's wrong)
     get_app_data()
          Get the application data (supplied via set_app_data())
              Returns The application data
     get_cert_store()
          Get the certificate store for the context. This can be used to add "trusted" certificates without using the
          load_verify_locations() method.
              Returns A X509Store object or None if it does not have one.
     get_session_cache_mode()
          Get the current session cache mode.
              Returns The currently used cache mode.
          New in version 0.14.
     get_timeout()
          Retrieve session timeout, as set by set timeout(). The default is 300 seconds.
              Returns The session timeout
     get_verify_depth()
          Retrieve the Context object's verify depth, as set by set_verify_depth().
              Returns The verify depth
     get_verify_mode()
          Retrieve the Context object's verify mode, as set by set_verify().
```

Load the trusted certificates that will be sent to the client. Does not actually imply any of the certificates

1.3. OpenSSL — Python interface to OpenSSL

are trusted; that must be configured separately.

Returns The verify mode

load_client_ca (cafile)

Parameters cafile (bytes) – The path to a certificates file in PEM format.

Returns None

load_tmp_dh (dhfile)

Load parameters for Ephemeral Diffie-Hellman

Parameters dhfile - The file to load EDH parameters from (bytes or unicode).

Returns None

load_verify_locations (cafile, capath=None)

Let SSL know where we can find trusted certificates for the certificate chain. Note that the certificates have to be in PEM format.

If capath is passed, it must be a directory prepared using the c_rehash tool included with OpenSSL. Either, but not both, of *pemfile* or *capath* may be None.

Parameters

- cafile In which file we can find the certificates (bytes or unicode).
- capath In which directory we can find the certificates (bytes or unicode).

Returns None

set_alpn_protos(protos)

Specify the protocols that the client is prepared to speak after the TLS connection has been negotiated using Application Layer Protocol Negotiation.

Parameters protos - A list of the protocols to be offered to the server. This list should be a Python list of bytestrings representing the protocols to offer, e.g. [b'http/1.1', b'spdy/2'].

set_alpn_select_callback(callback)

Specify a callback function that will be called on the server when a client offers protocols using ALPN.

Parameters callback – The callback function. It will be invoked with two arguments: the Connection, and a list of offered protocols as bytestrings, e.g [b'http/1.1', b'spdy/2']. It can return one of those bytestrings to indicate the chosen protocol, the empty bytestring to terminate the TLS connection, or the NO_OVERLAPPING_PROTOCOLS to indicate that no offered protocol was selected, but that the connection should not be aborted.

set_app_data(data)

Set the application data (will be returned from get_app_data())

Parameters data - Any Python object

Returns None

set_cipher_list (cipher_list)

Set the list of ciphers to be used in this context.

See the OpenSSL manual for more information (e.g. ciphers (1)).

Parameters cipher_list (bytes) - An OpenSSL cipher string.

Returns None

set_client_ca_list (certificate_authorities)

Set the list of preferred client certificate signers for this server context.

This list of certificate authorities will be sent to the client when the server requests a client certificate.

Parameters certificate_authorities – a sequence of X509Names.

Returns None

New in version 0.10.

set_default_verify_paths()

Specify that the platform provided CA certificates are to be used for verification purposes. This method has some caveats related to the binary wheels that cryptography (pyOpenSSL's primary dependency) ships:

- macOS will only load certificates using this method if the user has the openssl@1.1 Homebrew formula installed in the default location.
- · Windows will not work.
- manylinux1 cryptography wheels will work on most common Linux distributions in pyOpenSSL 17.1.0 and above. pyOpenSSL detects the manylinux1 wheel and attempts to load roots via a fall-back path.

Returns None

set_info_callback(callback)

Set the information callback to *callback*. This function will be called from time to time during SSL handshakes.

Parameters callback – The Python callback to use. This should take three arguments: a Connection object and two integers. The first integer specifies where in the SSL handshake the function was called, and the other the return code from a (possibly failed) internal function call.

Returns None

set_mode(mode)

Add modes via bitmask. Modes set before are not cleared! This method should be used with the MODE_* constants.

Parameters mode - The mode to add.

Returns The new mode bitmask.

set_npn_advertise_callback(callback)

Specify a callback function that will be called when offering Next Protocol Negotiation as a server.

Parameters callback – The callback function. It will be invoked with one argument, the *Connection* instance. It should return a list of bytestrings representing the advertised protocols, like [b'http/1.1', b'spdy/2'].

New in version 0.15.

set_npn_select_callback(callback)

Specify a callback function that will be called when a server offers Next Protocol Negotiation options.

Parameters callback – The callback function. It will be invoked with two arguments: the Connection, and a list of offered protocols as bytestrings, e.g. [b'http/1.1', b'spdy/2']. It should return one of those bytestrings, the chosen protocol.

New in version 0.15.

set ocsp client callback(callback, data=None)

Set a callback to validate OCSP data stapled to the TLS handshake on the client side.

Parameters

• callback – The callback function. It will be invoked with three arguments: the Connection, a bytestring containing the stapled OCSP assertion, and the optional arbitrary data

you have provided. The callback must return a boolean that indicates the result of validating the OCSP data: True if the OCSP data is valid and the certificate can be trusted, or False if either the OCSP data is invalid or the certificate has been revoked.

• data – Some opaque data that will be passed into the callback function when called. This can be used to avoid needing to do complex data lookups or to keep track of what context is being used. This parameter is optional.

set_ocsp_server_callback (callback, data=None)

Set a callback to provide OCSP data to be stapled to the TLS handshake on the server side.

Parameters

- callback The callback function. It will be invoked with two arguments: the Connection, and the optional arbitrary data you have provided. The callback must return a bytestring that contains the OCSP data to staple to the handshake. If no OCSP data is available for this connection, return the empty bytestring.
- data Some opaque data that will be passed into the callback function when called. This can be used to avoid needing to do complex data lookups or to keep track of what context is being used. This parameter is optional.

set_options (options)

Add options. Options set before are not cleared! This method should be used with the OP_* constants.

Parameters options – The options to add.

Returns The new option bitmask.

set passwd cb(callback, userdata=None)

Set the passphrase callback. This function will be called when a private key with a passphrase is loaded.

Parameters

- **callback** The Python callback to use. This must accept three positional arguments. First, an integer giving the maximum length of the passphrase it may return. If the returned passphrase is longer than this, it will be truncated. Second, a boolean value which will be true if the user should be prompted for the passphrase twice and the callback should verify that the two values supplied are equal. Third, the value given as the *userdata* parameter to $set_passwd_cb()$. The *callback* must return a byte string. If an error occurs, *callback* should return a false value (e.g. an empty string).
- userdata (optional) A Python object which will be given as argument to the callback

Returns None

$set_session_cache_mode(mode)$

Set the behavior of the session cache used by all connections using this Context. The previously set mode is returned. See SESS_CACHE_* for details about particular modes.

Parameters mode – One or more of the SESS_CACHE_* flags (combine using bitwise or)

Returns The previously set caching mode.

New in version 0.14.

set_session_id(buf)

Set the session id to *buf* within which a session can be reused for this Context object. This is needed when doing session resumption, because there is no way for a stored session to know which Context object it is associated with.

Parameters buf (bytes) - The session id.

Returns None

set timeout(timeout)

Set the timeout for newly created sessions for this Context object to *timeout*. The default value is 300 seconds. See the OpenSSL manual for more information (e.g. SSL CTX set timeout (3)).

Parameters timeout – The timeout in (whole) seconds

Returns The previous session timeout

set_tlsext_servername_callback(callback)

Specify a callback function to be called when clients specify a server name.

Parameters callback – The callback function. It will be invoked with one argument, the Connection instance.

New in version 0.13.

set_tlsext_use_srtp(profiles)

Enable support for negotiating SRTP keying material.

Parameters profiles (bytes) - A colon delimited list of protection profile names, like b'SRTP_AES128_CM_SHA1_80:SRTP_AES128_CM_SHA1_32'.

Returns None

set tmp ecdh(curve)

Select a curve to use for ECDHE key exchange.

Parameters curve - A curve object to use as returned by either OpenSSL.crypto. get_elliptic_curve() or OpenSSL.crypto.get_elliptic_curves().

Returns None

set_verify (mode, callback)

et the verification flags for this Context object to *mode* and specify that *callback* should be used for verification callbacks.

Parameters

- mode The verify mode, this should be one of VERIFY_NONE and VERIFY_PEER. If VERIFY_PEER is used, mode can be OR:ed with VERIFY_FAIL_IF_NO_PEER_CERT and VERIFY_CLIENT_ONCE to further control the behaviour.
- callback The Python callback to use. This should take five arguments: A Connection object, an X509 object, and three integer variables, which are in turn potential error number, error depth and return code. *callback* should return True if verification passes and False otherwise.

Returns None

See SSL_CTX_set_verify(3SSL) for further details.

set_verify_depth(depth)

Set the maximum depth for the certificate chain verification that shall be allowed for this Context object.

Parameters depth – An integer specifying the verify depth

Returns None

use_certificate(cert)

Load a certificate from a X509 object

Parameters cert - The X509 object

Returns None

use_certificate_chain_file(certfile)

Load a certificate chain from a file.

Parameters certfile - The name of the certificate chain file (bytes or unicode). Must be PEM encoded.

Returns None

use_certificate_file (certfile, filetype=1)

Load a certificate from a file

Parameters

- certfile The name of the certificate file (bytes or unicode).
- **filetype** (optional) The encoding of the file, which is either <code>FILETYPE_PEM</code> or <code>FILETYPE_ASN1</code>. The default is <code>FILETYPE_PEM</code>.

Returns None

use_privatekey(pkey)

Load a private key from a PKey object

Parameters pkey - The PKey object

Returns None

use_privatekey_file (keyfile, filetype=<object object>)

Load a private key from a file

Parameters

- **keyfile** The name of the key file (bytes or unicode)
- **filetype** (optional) The encoding of the file, which is either <code>FILETYPE_PEM</code> or <code>FILETYPE_ASN1</code>. The default is <code>FILETYPE_PEM</code>.

Returns None

Session objects

Session objects have no methods.

Connection objects

Connection objects have the following methods:

```
class OpenSSL.SSL.Connection(context, socket=None)
```

```
accept()
```

Call the accept () method of the underlying socket and set up SSL on the returned socket, using the Context object supplied to this Connection object at creation.

Returns A (conn, addr) pair where conn is the new Connection object created, and address is as returned by the socket's accept ().

```
bio_read(bufsiz)
```

If the Connection was created with a memory BIO, this method can be used to read bytes from the write end of that memory BIO. Many Connection methods will add bytes which must be read in this manner or the buffer will eventually fill up and the Connection will be able to take no further actions.

Parameters bufsiz - The maximum number of bytes to read

Returns The string read.

bio_shutdown()

If the Connection was created with a memory BIO, this method can be used to indicate that *end of file* has been reached on the read end of that memory BIO.

Returns None

bio_write(buf)

If the Connection was created with a memory BIO, this method can be used to add bytes to the read end of that memory BIO. The Connection can then read the bytes (for example, in response to a call to recv()).

Parameters buf – The string to put into the memory BIO.

Returns The number of bytes written

client_random()

Retrieve the random value used with the client hello message.

Returns A string representing the state

connect (addr)

Call the <code>connect()</code> method of the underlying socket and set up SSL on the socket, using the <code>Context</code> object supplied to this <code>Connection</code> object at creation.

Parameters addr – A remote address

Returns What the socket's connect method returns

connect ex(addr)

Call the <code>connect_ex()</code> method of the underlying socket and set up SSL on the socket, using the Context object supplied to this Connection object at creation. Note that if the <code>connect_ex()</code> method of the socket doesn't return 0, SSL won't be initialized.

Parameters addr - A remove address

Returns What the socket's connect_ex method returns

do handshake()

Perform an SSL handshake (usually called after renegotiate() or one of set_accept_state() or set_connect_state()). This can raise the same exceptions as send() and recv().

Returns None.

export_keying_material (label, olen, context=None)

Obtain keying material for application use.

Param label - a disambiguating label string as described in RFC 5705

Param olen - the length of the exported key material in bytes

Param context - a per-association context value

Returns the exported key material bytes or None

get_alpn_proto_negotiated()

Get the protocol that was negotiated by ALPN.

Returns A bytestring of the protocol name. If no protocol has been negotiated yet, returns an empty string.

get_app_data()

Retrieve application data as set by set_app_data().

Returns The application data

get certificate()

Retrieve the local certificate (if any)

Returns The local certificate

get cipher bits()

Obtain the number of secret bits of the currently used cipher.

Returns The number of secret bits of the currently used cipher or None if no connection has been established.

Return type int or NoneType

New in version 0.15.

get_cipher_list()

Retrieve the list of ciphers used by the Connection object.

Returns A list of native cipher strings.

get_cipher_name()

Obtain the name of the currently used cipher.

Returns The name of the currently used cipher or None if no connection has been established.

Return type unicode or NoneType

New in version 0.15.

get_cipher_version()

Obtain the protocol version of the currently used cipher.

Returns The protocol name of the currently used cipher or None if no connection has been established.

Return type unicode or NoneType

New in version 0.15.

get_client_ca_list()

Get CAs whose certificates are suggested for client authentication.

Returns

If this is a server connection, the list of certificate authorities that will be sent or has been sent to the client, as controlled by this Connection's Context.

If this is a client connection, the list will be empty until the connection with the server is established.

New in version 0.10.

get_context()

Retrieve the Context object associated with this Connection.

get_finished()

Obtain the latest TLS Finished message that we sent.

Returns The contents of the message or None if the TLS handshake has not yet completed.

Return type bytes or NoneType

New in version 0.15.

get_next_proto_negotiated()

Get the protocol that was negotiated by NPN.

Returns A bytestring of the protocol name. If no protocol has been negotiated yet, returns an empty string.

New in version 0.15.

get_peer_cert_chain()

Retrieve the other side's certificate (if any)

Returns A list of X509 instances giving the peer's certificate chain, or None if it does not have one

get_peer_certificate()

Retrieve the other side's certificate (if any)

Returns The peer's certificate

get_peer_finished()

Obtain the latest TLS Finished message that we received from the peer.

Returns The contents of the message or None if the TLS handshake has not yet completed.

Return type bytes or NoneType

New in version 0.15.

get_protocol_version()

Retrieve the SSL or TLS protocol version of the current connection.

Returns The TLS version of the current connection. For example, it will return 0x769 for connections made over TLS version 1.

Return type int

get_protocol_version_name()

Retrieve the protocol version of the current connection.

Returns The TLS version of the current connection, for example the value for TLS 1.2 would be TLSv1.2``or```Unknown for connections that were not successfully established.

Return type unicode

get_servername()

Retrieve the servername extension value if provided in the client hello message, or None if there wasn't

Returns A byte string giving the server name or None.

New in version 0.13.

get session()

Returns the Session currently used.

Returns An instance of OpenSSL.SSL.Session or None if no session exists.

New in version 0.14.

${\tt get_shutdown}\;(\,)$

Get the shutdown state of the Connection.

Returns The shutdown state, a bitvector of SENT_SHUTDOWN, RECEIVED_SHUTDOWN.

get_state_string()

Retrieve a verbose string detailing the state of the Connection.

Returns A string representing the state

Return type bytes

```
makefile (*args, **kwargs)
```

The makefile() method is not implemented, since there is no dup semantics for SSL connections

Raise NotImplementedError

master_key()

Retrieve the value of the master key for this session.

Returns A string representing the state

pending()

Get the number of bytes that can be safely read from the SSL buffer (**not** the underlying transport buffer).

Returns The number of bytes available in the receive buffer.

```
read (bufsiz, flags=None)
```

Receive data on the connection.

Parameters

- bufsiz The maximum number of bytes to read
- **flags** (optional) The only supported flag is MSG_PEEK, all other flags are ignored.

Returns The string read from the Connection

```
recv (bufsiz, flags=None)
```

Receive data on the connection.

Parameters

- bufsiz The maximum number of bytes to read
- flags (optional) The only supported flag is MSG_PEEK, all other flags are ignored.

Returns The string read from the Connection

```
recv_into (buffer, nbytes=None, flags=None)
```

Receive data on the connection and copy it directly into the provided buffer, rather than creating a new string.

Parameters

- **buffer** The buffer to copy into.
- **nbytes** (optional) The maximum number of bytes to read into the buffer. If not present, defaults to the size of the buffer. If larger than the size of the buffer, is reduced to the size of the buffer.
- **flags** (optional) The only supported flag is MSG_PEEK, all other flags are ignored.

Returns The number of bytes read into the buffer.

renegotiate()

Renegotiate the session.

Returns True if the renegotiation can be started, False otherwise

Return type bool

renegotiate_pending()

Check if there's a renegotiation in progress, it will return False once a renegotiation is finished.

Returns Whether there's a renegotiation in progress

Return type bool

request_ocsp()

Called to request that the server sends stapled OCSP data, if available. If this is not called on the client side then the server will not send OCSP data. Should be used in conjunction with <code>Context.set_ocsp_client_callback()</code>.

send(buf, flags=0)

Send data on the connection. NOTE: If you get one of the WantRead, WantWrite or WantX509Lookup exceptions on this, you have to call the method again with the SAME buffer.

Parameters

- **buf** The string, buffer or memoryview to send
- flags (optional) Included for compatibility with the socket API, the value is ignored

Returns The number of bytes written

sendall(buf, flags=0)

Send "all" data on the connection. This calls send() repeatedly until all data is sent. If an error occurs, it's impossible to tell how much data has been sent.

Parameters

- **buf** The string, buffer or memoryview to send
- flags (optional) Included for compatibility with the socket API, the value is ignored

Returns The number of bytes written

server random()

Retrieve the random value used with the server hello message.

Returns A string representing the state

set_accept_state()

Set the connection to work in server mode. The handshake will be handled automatically by read/write.

Returns None

set_alpn_protos (protos)

Specify the client's ALPN protocol list.

These protocols are offered to the server during protocol negotiation.

Parameters protos - A list of the protocols to be offered to the server. This list should be a Python list of bytestrings representing the protocols to offer, e.g. [b'http/1.1', b'spdy/2'].

set_app_data(data)

Set application data

Parameters data – The application data

Returns None

set_connect_state()

Set the connection to work in client mode. The handshake will be handled automatically by read/write.

Returns None

set_context (context)

Switch this connection to a new session context.

Parameters context - A Context instance giving the new session context to use.

set session(session)

Set the session to be used when the TLS/SSL connection is established.

Parameters session – A Session instance representing the session to use.

Returns None

New in version 0.14.

set shutdown (state)

Set the shutdown state of the Connection.

Parameters state - bitvector of SENT_SHUTDOWN, RECEIVED_SHUTDOWN.

Returns None

set_tlsext_host_name (name)

Set the value of the servername extension to send in the client hello.

Parameters name – A byte string giving the name.

New in version 0.13.

shutdown()

Send the shutdown message to the Connection.

Returns True if the shutdown completed successfully (i.e. both sides have sent closure alerts), False otherwise (in which case you call recv() or send() when the connection becomes readable/writeable).

sock_shutdown (*args, **kwargs)

Call the shutdown () method of the underlying socket. See shutdown (2).

Returns What the socket's shutdown() method returns

total_renegotiations()

Find out the total number of renegotiations.

Returns The number of renegotiations.

Return type int

want_read()

Checks if more data has to be read from the transport layer to complete an operation.

Returns True iff more data has to be read

want write()

Checks if there is data to write to the transport layer to complete an operation.

Returns True iff there is data to write

write (buf, flags=0)

Send data on the connection. NOTE: If you get one of the WantRead, WantWrite or WantX509Lookup exceptions on this, you have to call the method again with the SAME buffer.

Parameters

- **buf** The string, buffer or memoryview to send
- flags (optional) Included for compatibility with the socket API, the value is ignored

Returns The number of bytes written

1.4 Internals

We ran into three main problems developing this: Exceptions, callbacks and accessing socket methods. This is what this chapter is about.

1.4.1 Exceptions

We realized early that most of the exceptions would be raised by the I/O functions of OpenSSL, so it felt natural to mimic OpenSSL's error code system, translating them into Python exceptions. This naturally gives us the exceptions SSL.ZeroReturnError, SSL.WantReadError, SSL.WantWriteError, SSL.WantX509LookupError and SSL.SysCallError.

For more information about this, see section SSL — An interface to the SSL-specific parts of OpenSSL.

1.4.2 Callbacks

Callbacks were more of a problem when pyOpenSSL was written in C. Having switched to being written in Python using cffi, callbacks are now straightforward. The problems that originally existed no longer do (if you are interested in the details you can find descriptions of those problems in the version control history for this document).

1.4.3 Accessing Socket Methods

We quickly saw the benefit of wrapping socket methods in the SSL.Connection class, for an easy transition into using SSL. The problem here is that the socket module lacks a C API, and all the methods are declared static. One approach would be to have OpenSSL as a submodule to the socket module, placing all the code in socketmodule.c, but this is obviously not a good solution, since you might not want to import tonnes of extra stuff you're not going to use when importing the socket module. The other approach is to somehow get a pointer to the method to be called, either the C function, or a callable Python object. This is not really a good solution either, since there's a lot of lookups involved.

The way it works is that you have to supply a <code>socket-like</code> transport object to the <code>SSL.Connection</code>. The only requirement of this object is that it has a <code>fileno()</code> method that returns a file descriptor that's valid at the C level (i.e. you can use the system calls read and write). If you want to use the <code>connect()</code> or <code>accept()</code> methods of the <code>SSL.Connection</code> object, the transport object has to supply such methods too. Apart from them, any method lookups in the <code>SSL.Connection</code> object that fail are passed on to the underlying transport object.

Future changes might be to allow Python-level transport objects, that instead of having fileno() methods, have read() and write() methods, so more advanced features of Python can be used. This would probably entail some sort of OpenSSL BIOs, but converting Python strings back and forth is expensive, so this shouldn't be used unless necessary. Other nice things would be to be able to pass in different transport objects for reading and writing, but then the fileno() method of SSL.Connection becomes virtually useless. Also, should the method resolution be used on the read-transport or the write-transport?

There are also examples in the pyOpenSSL repository that may help you getting started.

1.5 Meta

1.5.1 Backward Compatibility

pyOpenSSL has a very strong backward compatibility policy. Generally speaking, you shouldn't ever be afraid of updating.

1.4. Internals 41

If breaking changes are needed do be done, they are:

- 1. ... announced in the *Changelog*.
- 2. ...the old behavior raises a DeprecationWarning for a year.
- 3. ... are done with another announcement in the *Changelog*.

1.5.2 Changelog

Versions are year-based with a strict backward-compatibility policy. The third digit is only for regressions.

19.1.0 (2019-11-18)

Backward-incompatible changes:

- Removed deprecated ContextType, ConnectionType, PKeyType, X509NameType, X509ReqType, X509Type, X509StoreType, CRLType, PKCS7Type, PKCS12Type, and NetscapeSPKIType aliases. Use the classes without the Type suffix instead. #814
- The minimum cryptography version is now 2.8 due to issues on macOS with a transitive dependency. #875

Deprecations:

• Deprecated OpenSSL.SSL.Context.set_npn_advertise_callback, OpenSSL. SSL.Context.set_npn_select_callback, and OpenSSL.SSL.Connection. get_next_proto_negotiated. ALPN should be used instead. #820

Changes:

- Support bytearray in SSL.Connection.send() by using cffi's from_buffer. #852
- The OpenSSL.SSL.Context.set_alpn_select_callback can return a new NO_OVERLAPPING_PROTOCOLS sentinel value to allow a TLS handshake to complete without an application protocol.

19.0.0 (2019-01-21)

Backward-incompatible changes:

• X509Store.add_cert no longer raises an error if you add a duplicate cert. #787

Deprecations:

none

Changes:

- pyOpenSSL now works with OpenSSL 1.1.1. #805
- pyOpenSSL now handles NUL bytes in X509Name.get_components() #804

18.0.0 (2018-05-16)

Backward-incompatible changes:

- The minimum cryptography version is now 2.2.1.
- Support for Python 2.6 has been dropped.

Deprecations:

none

Changes:

- Added Connection.get_certificate to retrieve the local certificate. #733
- OpenSSL.SSL.Connection now sets SSL_MODE_AUTO_RETRY by default. #753
- Added Context.set_tlsext_use_srtp to enable negotiation of SRTP keying material. #734

17.5.0 (2017-11-30)

Backward-incompatible changes:

• The minimum cryptography version is now 2.1.4.

Deprecations:

none

Changes:

- Fixed a potential use-after-free in the verify callback and resolved a memory leak when loading PKCS12 files with cacerts. #723
- Added Connection.export_keying_material for RFC 5705 compatible export of keying material. #725

1.5. Meta 43

17.4.0 (2017-11-21)

Backward-incompatible changes:

none

Deprecations:

none

Changes:

- Re-added a subset of the OpenSSL.rand module. This subset allows conscientious users to reseed the OpenSSL CSPRNG after fork. #708
- Corrected a use-after-free when reusing an issuer or subject from an X509 object after the underlying object has been mutated. #709

17.3.0 (2017-09-14)

Backward-incompatible changes:

- Dropped support for Python 3.3. #677
- Removed the deprecated OpenSSL.rand module. This is being done ahead of our normal deprecation schedule due to its lack of use and the fact that it was becoming a maintenance burden. os.urandom() should be used instead. #675

Deprecations:

• Deprecated OpenSSL.tsafe. #673

Changes:

- Fixed a memory leak in OpenSSL.crypto.CRL.#690
- Fixed a memory leak when verifying certificates with OpenSSL.crypto.X509StoreContext. #691

17.2.0 (2017-07-20)

Backward-incompatible changes:

none

Deprecations:

• Deprecated OpenSSL.rand - callers should use os.urandom() instead. #658

Changes:

- Fixed a bug causing Context.set_default_verify_paths() to not work with cryptography manylinux1 wheels on Python 3.x. #665
- Fixed a crash with (EC)DSA signatures in some cases. #670

17.1.0 (2017-06-30)

Backward-incompatible changes:

- Removed the deprecated OpenSSL.rand.egd() function. Applications should prefer os.urandom() for random number generation. #630
- Removed the deprecated default digest argument to OpenSSL.crypto.CRL.export(). Callers must now always pass an explicit digest. #652
- Fixed a bug with ASN1_TIME casting in X509.set_notBefore(), X509.set_notAfter(), Revoked.set_rev_date(), Revoked.set_nextUpdate(), and Revoked.set_lastUpdate(). You must now pass times in the form YYYYMMDDhhmmssZ.YYYYMMDDhhmmss+hhmm and YYYYMMDDhhmmss-hhmm will no longer work.#612

Deprecations:

• Deprecated the legacy "Type" aliases: ContextType, ConnectionType, PKeyType, X509NameType, X509ExtensionType, X509ReqType, X509Type, X509StoreType, CRLType, PKCS7Type, PKCS12Type, NetscapeSPKIType. The names without the "Type"-suffix should be used instead.

Changes:

- Added OpenSSL.crypto.X509.from_cryptography() and OpenSSL.crypto.X509. to_cryptography() for converting X.509 certificate to and from pyca/cryptography objects. #640
- Added OpenSSL.crypto.X509Req.from_cryptography(), OpenSSL.crypto.X509Req.to_cryptography(), OpenSSL.crypto.CRL.from_cryptography(), and OpenSSL.crypto.CRL.to_cryptography() for converting X.509 CSRs and CRLs to and from pyca/cryptography objects. #645
- Added OpenSSL.debug that allows to get an overview of used library versions (including linked OpenSSL) and other useful runtime information using python -m OpenSSL.debug. #620
- Added a fallback path to Context.set_default_verify_paths() to accommodate the upcoming release of cryptography manylinux1 wheels. #633

1.5. Meta 45

17.0.0 (2017-04-20)

Backward-incompatible changes:

none

Deprecations:

none

Changes:

- Added OpenSSL.X509Store.set_time() to set a custom verification time when verifying certificate chains. #567
- Added a collection of functions for working with OCSP stapling. None of these functions make it possible to validate OCSP assertions, only to staple them into the handshake and to retrieve the stapled assertion if provided. Users will need to write their own code to handle OCSP assertions. We specifically added: Context.set_ocsp_server_callback(), Context.set_ocsp_client_callback(), and Connection.request_ocsp().#580
- Changed the SSL module's memory allocation policy to avoid zeroing memory it allocates when unnecessary.
 This reduces CPU usage and memory allocation time by an amount proportional to the size of the allocation.
 For applications that process a lot of TLS data or that use very lage allocations this can provide considerable performance improvements. #578
- Automatically set SSL_CTX_set_ecdh_auto() on OpenSSL.SSL.Context. #575
- Fix empty exceptions from OpenSSL.crypto.load_privatekey().#581

16.2.0 (2016-10-15)

Backward-incompatible changes:

none

Deprecations:

none

Changes:

- Fixed compatibility errors with OpenSSL 1.1.0.
- Fixed an issue that caused failures with subinterpreters and embedded Pythons. #552

16.1.0 (2016-08-26)

Backward-incompatible changes:

none

Deprecations:

• Dropped support for OpenSSL 0.9.8.

Changes:

- Fix memory leak in OpenSSL.crypto.dump_privatekey() with FILETYPE_TEXT. #496
- Enable use of CRL (and more) in verify context. #483
- OpenSSL.crypto.PKey can now be constructed from cryptography objects and also exported as such. #439
- Support newer versions of cryptography which use opaque structs for OpenSSL 1.1.0 compatibility.

16.0.0 (2016-03-19)

This is the first release under full stewardship of PyCA. We have made *many* changes to make local development more pleasing. The test suite now passes both on Linux and OS X with OpenSSL 0.9.8, 1.0.1, and 1.0.2. It has been moved to pytest, all CI test runs are part of tox and the source code has been made fully flake8 compliant.

We hope to have lowered the barrier for contributions significantly but are open to hear about any remaining frustrations.

Backward-incompatible changes:

• Python 3.2 support has been dropped. It never had significant real world usage and has been dropped by our main dependency cryptography. Affected users should upgrade to Python 3.3 or later.

Deprecations:

• The support for EGD has been removed. The only affected function <code>OpenSSL.rand.egd()</code> now uses <code>os.urandom()</code> to seed the internal PRNG instead. Please see <code>pyca/cryptography#1636</code> for more background information on this decision. In accordance with our backward compatibility <code>policy OpenSSL.rand.egd()</code> will be <code>removed</code> no sooner than a year from the release of 16.0.0.

Please note that you should use urandom for all your secure random number needs.

• Python 2.6 support has been deprecated. Our main dependency cryptography deprecated 2.6 in version 0.9 (2015-05-14) with no time table for actually dropping it. pyOpenSSL will drop Python 2.6 support once cryptography does.

1.5. Meta 47

Changes:

- Fixed OpenSSL.SSL.Context.set_session_id, OpenSSL.SSL.Connection.renegotiate, OpenSSL.SSL.Connection.renegotiate_pending, and OpenSSL.SSL.Context. load_client_ca. They were lacking an implementation since 0.14. #422
- Fixed segmentation fault when using keys larger than 4096-bit to sign data. #428
- Fixed AttributeError when OpenSSL.SSL.Connection.get_app_data() was called before setting any app data. #304
- Added OpenSSL.crypto.dump_publickey() to dump OpenSSL.crypto.PKey objects that represent public keys, and OpenSSL.crypto.load_publickey() to load such objects from serialized representations. #382
- Added OpenSSL.crypto.dump_crl() to dump a certificate revocation list out to a string buffer. #368
- Added OpenSSL.SSL.Connection.get_state_string() using the OpenSSL binding state_string_long.#358
- Added support for the socket.MSG_PEEK flag to OpenSSL.SSL.Connection.recv() and OpenSSL.SSL.Connection.recv_into().#294
- Added OpenSSL.SSL.Connection.get_protocol_version() and OpenSSL.SSL. Connection.get_protocol_version_name().#244
- Switched to utf8string mask by default. OpenSSL formerly defaulted to a T61String if there were UTF-8 characters present. This was changed to default to UTF8String in the config around 2005, but the actual code didn't change it until late last year. This will default us to the setting that actually works. To revert this you can call OpenSSL.crypto._lib.ASN1_STRING_set_default_mask_asc(b"default"). #234

Older Changelog Entries

The changes from before release 16.0.0 are preserved in the repository.

CHAPTER 2

Indices and tables

- genindex
- modindex
- search

Python Module Index

0

OpenSSL.6
OpenSSL.crypto,6
OpenSSL.SSL,26

52 Python Module Index

Symbols init() (OpenSSL.crypto.CRL method), 23init() (OpenSSL.crypto.NetscapeSPKI method), 22init() (OpenSSL.crypto.X509Extension method), 21init() (OpenSSL.crypto.X509Name method), 14init() (OpenSSL.crypto.X509Req method), 14setattr() (OpenSSL.crypto.X509Name method), 14str() (OpenSSL.crypto.X509Extension method), 21	check_privatekey() (OpenSSL.SSL.Context method), 29 client_random() (OpenSSL.SSL.Connection method), 35 connect() (OpenSSL.SSL.Connection method), 35 connect_ex() (OpenSSL.SSL.Connection method), 35 Connection (class in OpenSSL.SSL), 28, 34 ConnectionType (in module OpenSSL.SSL), 27 Context (class in OpenSSL.SSL), 27, 28 ContextType (in module OpenSSL.SSL), 27 CRL (class in OpenSSL.crypto), 23
A	D
accept() (OpenSSL.SSL.Connection method), 34 add_cert() (OpenSSL.crypto.X509Store method), 16 add_client_ca() (OpenSSL.SSL.Context method), 29	der() (OpenSSL.crypto.X509Name method), 14 digest() (OpenSSL.crypto.X509 method), 10 do_handshake() (OpenSSL.SSL.Connection method), 35
add_crl() (OpenSSL.crypto.X509Store method), 16 add_extensions() (OpenSSL.crypto.X509 method), 10	<pre>dump_certificate() (in module OpenSSL.crypto),</pre>
add_extensions() (OpenSSL.crypto.X509Req method), 15	OpenSSL.crypto), 7 dump_crl() (in module OpenSSL.crypto), 9
add_extra_chain_cert() (OpenSSL.SSL.Context method), 29	dump_privatekey() (in module OpenSSL.crypto), 8 dump_publickey() (in module OpenSSL.crypto), 8
<pre>add_revoked() (OpenSSL.crypto.CRL method), 23 all_reasons() (OpenSSL.crypto.Revoked method),</pre>	Error, 25, 28 export () (OpenSSL.crypto.CRL method), 23
В	export () (OpenSSL.crypto.PKCS12 method), 20
b64_encode() (OpenSSL.crypto.NetscapeSPKI method), 22	<pre>export_keying_material() (OpenSSL.SSL.Connection method), 35</pre>
bio_read() (OpenSSL.SSL.Connection method), 34 bio_shutdown() (OpenSSL.SSL.Connection	F
method), 35	FILETYPE_ASN1 (in module OpenSSL.crypto), 7 FILETYPE_ASN1 (in module OpenSSL.SSL), 26
bio_write() (OpenSSL.SSL.Connection method), 35 bits() (OpenSSL.crypto.PKey method), 18	FILETYPE_ASN1 (in module OpenSSL.SSL), 20 FILETYPE_PEM (in module OpenSSL.crypto), 7
С	FILETYPE_PEM (in module OpenSSL.SSL), 26 from_cryptography() (OpenSSL.crypto.CRL class method), 23
check () (OpenSSL.crypto.PKey method), 18	memoa), 45

from_cryptography() (OpenSSL.crypto.X509	<pre>get_issuer() (OpenSSL.crypto.CRL method), 23</pre>
class method), 10	<pre>get_issuer() (OpenSSL.crypto.X509 method), 11</pre>
from_cryptography() (OpenSSL.crypto.X509Req	<pre>get_next_proto_negotiated()</pre>
class method), 15	(OpenSSL.SSL.Connection method), 36
from_cryptography_key()	get_notAfter() (OpenSSL.crypto.X509 method), 11
(OpenSSL.crypto.PKey class method), 19	<pre>get_notBefore() (OpenSSL.crypto.X509 method),</pre>
G	get_peer_cert_chain()
<pre>generate_key() (OpenSSL.crypto.PKey method), 19</pre>	(OpenSSL.SSL.Connection method), 37
get_alpn_proto_negotiated()	<pre>get_peer_certificate()</pre>
(OpenSSL.SSL.Connection method), 35	(OpenSSL.SSL.Connection method), 37
get_app_data() (OpenSSL.SSL.Connection	<pre>get_peer_finished() (OpenSSL.SSL.Connection</pre>
method), 35	method), 37
<pre>get_app_data() (OpenSSL.SSL.Context method), 29</pre>	get_privatekey() (OpenSSL.crypto.PKCS12
get_ca_certificates()	method), 20
(OpenSSL.crypto.PKCS12 method), 20	get_protocol_version()
<pre>get_cert_store() (OpenSSL.SSL.Context method),</pre>	(OpenSSL.SSL.Connection method), 37 get_protocol_version_name()
29 (O) CCI (O) PECCI (O)	(OpenSSL.SSL.Connection method), 37
get_certificate() (OpenSSL.crypto.PKCS12	get_pubkey() (OpenSSL.crypto.NetscapeSPKI
<pre>method), 20 get_certificate() (OpenSSL.SSL.Connection</pre>	method), 22
<pre>get_certificate() (OpenSSL.SSL.Connection method), 35</pre>	get_pubkey() (OpenSSL.crypto.X509 method), 11
get_cipher_bits() (OpenSSL.SSL.Connection	get_pubkey() (OpenSSL.crypto.X509Req method),
method), 36	15
<pre>get_cipher_list() (OpenSSL.SSL.Connection</pre>	<pre>get_reason() (OpenSSL.crypto.Revoked method), 25</pre>
method), 36	<pre>get_rev_date() (OpenSSL.crypto.Revoked method),</pre>
<pre>get_cipher_name() (OpenSSL.SSL.Connection</pre>	25
method), 36	<pre>get_revoked() (OpenSSL.crypto.CRL method), 23</pre>
<pre>get_cipher_version() (OpenSSL.SSL.Connection</pre>	get_serial() (OpenSSL.crypto.Revoked method), 25
method), 36	get_serial_number() (OpenSSL.crypto.X509
<pre>get_client_ca_list() (OpenSSL.SSL.Connection</pre>	<pre>method), 11 get_servername() (OpenSSL.SSL.Connection</pre>
method), 36	method), 37
<pre>get_components() (OpenSSL.crypto.X509Name method), 14</pre>	get_session() (OpenSSL.SSL.Connection method),
get_context() (OpenSSL.SSL.Connection method),	37
36	<pre>get_session_cache_mode()</pre>
<pre>get_critical() (OpenSSL.crypto.X509Extension</pre>	(OpenSSL.SSL.Context method), 29
method), 21	<pre>get_short_name() (OpenSSL.crypto.X509Extension</pre>
<pre>get_data() (OpenSSL.crypto.X509Extension</pre>	method), 22
method), 21	get_shutdown() (OpenSSL.SSL.Connection
get_elliptic_curve() (in module	method), 37
OpenSSL.crypto), 6	get_signature_algorithm()
get_elliptic_curves() (in module	(OpenSSL.crypto.X509 method), 11 get_state_string() (OpenSSL.SSL.Connection
OpenSSL.crypto), 6	<pre>get_state_string() (OpenSSL.SSL.Connection method), 37</pre>
<pre>get_extension() (OpenSSL.crypto.X509 method), 10</pre>	get_subject() (OpenSSL.crypto.X509 method), 12
<pre>get_extension_count() (OpenSSL.crypto.X509</pre>	get_subject() (OpenSSL.crypto.X509Req method),
method), 10	15
get_extensions() (OpenSSL.crypto.X509Req	<pre>get_timeout() (OpenSSL.SSL.Context method), 29</pre>
method), 15	get_type_name() (OpenSSL.crypto.PKCS7
<pre>get_finished() (OpenSSL.SSL.Connection</pre>	method), 19
method), 36	<pre>get_verify_depth() (OpenSSL.SSL.Context</pre>
<pre>get_friendlyname() (OpenSSL.crypto.PKCS12</pre>	method), 29
method), 20	<pre>get_verify_mode()</pre> (OpenSSL.SSL.Context

```
method), 29
                                                 OpenSSL.SSL (module), 26
get_version() (OpenSSL.crypto.X509 method), 12
                                                 OPENSSL VERSION NUMBER
                                                                                  (in
                                                                                          module
get version() (OpenSSL.crypto.X509Reg method),
                                                          OpenSSL.SSL), 27
                                                 Р
                            (OpenSSL.crypto.X509
gmtime_adj_notAfter()
        method), 12
                                                 pending() (OpenSSL.SSL.Connection method), 38
gmtime adj notBefore() (OpenSSL.crypto.X509
                                                 PKCS12 (class in OpenSSL.crypto), 20
        method), 12
                                                 PKCS7 (class in OpenSSL.crypto), 19
                                                 PKey (class in OpenSSL.crypto), 18
Н
                                                 R
has expired() (OpenSSL.crypto.X509 method), 12
hash () (OpenSSL.crypto.X509Name method), 14
                                                 read() (OpenSSL.SSL.Connection method), 38
                                                 recv() (OpenSSL.SSL.Connection method), 38
L
                                                 recv_into() (OpenSSL.SSL.Connection method), 38
load certificate() (in module OpenSSL.crypto),
                                                 renegotiate() (OpenSSL.SSL.Connection method),
load_certificate_request()
                                   (in
                                         module
                                                 renegotiate_pending()
                                                         (OpenSSL.SSL.Connection method), 38
        OpenSSL.crypto), 7
load_client_ca() (OpenSSL.SSL.Context method),
                                                                          (OpenSSL.SSL.Connection
                                                 request ocsp()
                                                         method), 38
load_crl() (in module OpenSSL.crypto), 9
                                                 Revoked (class in OpenSSL.crypto), 24
load_pkcs12() (in module OpenSSL.crypto), 9
                                                 S
load_pkcs7_data() (in module OpenSSL.crypto), 9
load_privatekey() (in module OpenSSL.crypto), 8
                                                 send() (OpenSSL.SSL.Connection method), 39
load publickey() (in module OpenSSL.crypto), 8
                                                 sendall() (OpenSSL.SSL.Connection method), 39
load_tmp_dh() (OpenSSL.SSL.Context method), 30
                                                                          (OpenSSL.SSL.Connection
                                                 server_random()
load verify locations()
                                                         method), 39
        (OpenSSL.SSL.Context method), 30
                                                 SESS_CACHE_BOTH (in module OpenSSL.SSL), 27
                                                 SESS_CACHE_CLIENT (in module OpenSSL.SSL), 27
M
                                                 SESS_CACHE_NO_AUTO_CLEAR
                                                                                          module
                                                                                   (in
makefile() (OpenSSL.SSL.Connection method), 37
                                                          OpenSSL.SSL), 27
master_key() (OpenSSL.SSL.Connection method),
                                                 SESS_CACHE_NO_INTERNAL
                                                                                  (in
                                                                                          module
        38
                                                          OpenSSL.SSL), 27
                                                 SESS_CACHE_NO_INTERNAL_LOOKUP (in module
Ν
                                                          OpenSSL.SSL), 27
NetscapeSPKI (class in OpenSSL.crypto), 22
                                                 SESS_CACHE_NO_INTERNAL_STORE
NO_OVERLAPPING_PROTOCOLS
                                                         OpenSSL.SSL), 27
                                  (in
                                         module
        OpenSSL.SSL), 27
                                                 SESS CACHE OFF (in module OpenSSL.SSL), 27
                                                 SESS_CACHE_SERVER (in module OpenSSL.SSL), 27
0
                                                 Session (class in OpenSSL.SSL), 27
                                                 set_accept_state()
                                                                          (OpenSSL.SSL.Connection
OP_EPHEMERAL_RSA (in module OpenSSL.SSL), 26
                                                         method), 39
OP_NO_COMPRESSION (in module OpenSSL.SSL), 26
                                                 set_alpn_protos()
                                                                          (OpenSSL.SSL.Connection
OP_NO_SSLv2 (in module OpenSSL.SSL), 26
                                                         method), 39
OP_NO_SSLv3 (in module OpenSSL.SSL), 26
                                                 set_alpn_protos()
                                                                             (OpenSSL.SSL.Context
OP_NO_TICKET (in module OpenSSL.SSL), 26
                                                         method), 30
OP_NO_TLSv1 (in module OpenSSL.SSL), 26
                                                 set_alpn_select_callback()
OP_NO_TLSv1_1 (in module OpenSSL.SSL), 26
                                                         (OpenSSL.SSL.Context method), 30
OP_NO_TLSv1_2 (in module OpenSSL.SSL), 26
                                                 set_app_data()
                                                                          (OpenSSL.SSL.Connection
OP NO TLSv1 3 (in module OpenSSL.SSL), 26
                                                         method), 39
OP_SINGLE_DH_USE (in module OpenSSL.SSL), 26
                                                 set_app_data() (OpenSSL.SSL.Context method), 30
OP SINGLE ECDH USE (in module OpenSSL.SSL), 26
                                                 set_ca_certificates()
OpenSSL (module), 6
                                                          (OpenSSL.crypto.PKCS12 method), 21
OpenSSL.crypto (module), 6
```

set_certificate() (OpenSSL.crypto.PKCS12	(OpenSSL.SSL.Context method), 32
method), 21	<pre>set_session_id() (OpenSSL.SSL.Context method),</pre>
set_cipher_list() (OpenSSL.SSL.Context	32
method), 30	set_shutdown() (OpenSSL.SSL.Connection
<pre>set_client_ca_list() (OpenSSL.SSL.Context</pre>	method), 40
$\frac{1}{method}$, $\frac{1}{30}$	<pre>set_store() (OpenSSL.crypto.X509StoreContext</pre>
set_connect_state() (OpenSSL.SSL.Connection	method), 18
method), 39	set_subject() (OpenSSL.crypto.X509 method), 13
set_context() (OpenSSL.SSL.Connection method),	set_time() (OpenSSL.crypto.X509Store method), 17
39	
	set_timeout()(OpenSSL.SSL.Context method), 32
set_default_verify_paths()	set_tlsext_host_name()
(OpenSSL.SSL.Context method), 31	(OpenSSL.SSL.Connection method), 40
set_flags() (OpenSSL.crypto.X509Store method),	<pre>set_tlsext_servername_callback()</pre>
16	(OpenSSL.SSL.Context method), 33
set_friendlyname() (OpenSSL.crypto.PKCS12	<pre>set_tlsext_use_srtp() (OpenSSL.SSL.Context</pre>
method), 21	method), 33
<pre>set_info_callback() (OpenSSL.SSL.Context</pre>	<pre>set_tmp_ecdh() (OpenSSL.SSL.Context method), 33</pre>
method), 31	<pre>set_verify() (OpenSSL.SSL.Context method), 33</pre>
set_issuer() (OpenSSL.crypto.X509 method), 12	<pre>set_verify_depth() (OpenSSL.SSL.Context</pre>
set_lastUpdate() (OpenSSL.crypto.CRL method),	method), 33
23	<pre>set_version() (OpenSSL.crypto.CRL method), 24</pre>
set_mode() (OpenSSL.SSL.Context method), 31	set_version() (OpenSSL.crypto.X509 method), 13
<pre>set_nextUpdate() (OpenSSL.crypto.CRL method),</pre>	set_version() (OpenSSL.crypto.X509Req method),
24	15
set_notAfter() (OpenSSL.crypto.X509 method), 12	shutdown () (OpenSSL.SSL.Connection method), 40
set_notBefore() (OpenSSL.crypto.X509 method),	sign () (in module OpenSSL.crypto), 9
12.	sign() (OpenSSL.crypto.CRL method), 24
set_npn_advertise_callback()	sign () (OpenSSL.crypto.NetscapeSPKI method), 22
(OpenSSL.SSL.Context method), 31	sign () (OpenSSL.crypto.X509 method), 13
· ·	sign() (OpenSSL.crypto.X509 method), 15
set_npn_select_callback()	
(OpenSSL.SSL.Context method), 31	sock_shutdown() (OpenSSL.SSL.Connection
set_ocsp_client_callback()	method), 40
(OpenSSL.SSL.Context method), 31	SSLEAY_BUILT_ON (in module OpenSSLSSL), 27
set_ocsp_server_callback()	SSLEAY_CFLAGS (in module OpenSSL.SSL), 27
(OpenSSL.SSL.Context method), 32	SSLEAY_DIR (in module OpenSSLSSL), 27
set_options() (OpenSSL.SSL.Context method), 32	SSLEAY_PLATFORM (in module OpenSSL.SSL), 27
set_passwd_cb() (OpenSSL.SSL.Context method),	SSLEAY_VERSION (in module OpenSSL.SSL), 27
32	SSLeay_version() (in module OpenSSL.SSL), 27
set_privatekey() (OpenSSL.crypto.PKCS12	SSLv23_METHOD (in module OpenSSL.SSL), 26
method), 21	SSLv2_METHOD (in module OpenSSL.SSL), 26
set_pubkey() (OpenSSL.crypto.NetscapeSPKI	SSLv3_METHOD (in module OpenSSL.SSL), 26
method), 22	<pre>subject_name_hash() (OpenSSL.crypto.X509</pre>
set_pubkey() (OpenSSL.crypto.X509 method), 13	method), 13
set_pubkey() (OpenSSL.crypto.X509Req method),	SysCallError, 28
15	-
<pre>set_reason() (OpenSSL.crypto.Revoked method), 25</pre>	Т
<pre>set_rev_date() (OpenSSL.crypto.Revoked method),</pre>	TLSv1_1_METHOD (in module OpenSSL.SSL), 26
25	TLSv1_2_METHOD (in module OpenSSL.SSL), 26
<pre>set_serial() (OpenSSL.crypto.Revoked method), 25</pre>	TLSv1_METHOD (in module OpenSSL.SSL), 26
set_serial_number() (OpenSSL.crypto.X509	to_cryptography() (OpenSSL.crypto.CRL
method), 13	method), 24
set_session() (OpenSSL.SSL.Connection method),	to_cryptography() (OpenSSL.crypto.X509
39	method), 13
set session cache mode()	memory, 15

```
(OpenSSL.crypto.X509Req X509Extension (class in OpenSSL.crypto), 21
to_cryptography()
       method), 16
                                                X509Name (class in OpenSSL.crypto), 13
                           (OpenSSL.crypto.PKey
                                                X509Reg (class in OpenSSL.crypto), 14
to_cryptography_key()
       method), 19
                                                X509Store (class in OpenSSL.crypto), 16
total renegotiations()
                                                X509StoreContext (class in OpenSSL.crypto), 17
        (OpenSSL.SSL.Connection method), 40
                                                X509StoreContextError
                                                                                 (class
                                                                                             in
type () (OpenSSL.crypto.PKey method), 19
                                                        OpenSSL.crypto), 17
TYPE DSA (in module OpenSSL.crypto), 19
                                                X509StoreFlags (class in OpenSSL.crypto), 18
type_is_data() (OpenSSL.crypto.PKCS7 method),
                                                X509StoreFlags.ALLOW PROXY CERTS (in mod-
                                                        ule OpenSSL.crypto), 18
type_is_enveloped()
                          (OpenSSL.crypto.PKCS7
                                                X509StoreFlags.CB_ISSUER_CHECK (in module
                                                        OpenSSL.crypto), 18
       method), 20
                          (OpenSSL.crypto.PKCS7
                                                X509StoreFlags.CHECK_SS_SIGNATURE
type_is_signed()
                                                                                             (in
       method), 20
                                                        module OpenSSL.crypto), 18
type_is_signedAndEnveloped()
                                                X509StoreFlags.CRL_CHECK
                                                                                         module
                                                                                  (in
        (OpenSSL.crypto.PKCS7 method), 20
                                                        OpenSSL.crypto), 18
TYPE_RSA (in module OpenSSL.crypto), 19
                                                X509StoreFlags.CRL_CHECK_ALL (in module
                                                        OpenSSL.crypto), 18
U
                                                X509StoreFlags.EXPLICIT_POLICY (in module
                                                        OpenSSL.crypto), 18
use_certificate()
                           (OpenSSL.SSL.Context
                                                X509StoreFlags.IGNORE_CRITICAL (in module
       method), 33
                                                        OpenSSL.crypto), 18
use certificate chain file()
                                                X509StoreFlags.INHIBIT_MAP
                                                                                         module
                                                                                   (in
        (OpenSSL.SSL.Context method), 33
                                                        OpenSSL.crypto), 18
use_certificate_file() (OpenSSL.SSL.Context
                                                X509StoreFlags.NOTIFY_POLICY (in
                                                                                         module
       method), 34
                                                        OpenSSL.crypto), 18
use_privatekey() (OpenSSL.SSL.Context method),
                                                X509StoreFlags.POLICY_CHECK
                                                                                    (in
                                                                                         module
                                                        OpenSSL.crypto), 18
use_privatekey_file()
                           (OpenSSL.SSL.Context
                                                X509StoreFlags.X509_STRICT
                                                                                         module
                                                                                   (in
       method), 34
                                                        OpenSSL.crypto), 18
                                                Z
verify() (in module OpenSSL.crypto), 10
                                                ZeroReturnError, 28
verify() (OpenSSL.crypto.NetscapeSPKI method), 22
verify() (OpenSSL.crypto.X509Req method), 16
verify_certificate()
        (OpenSSL.crypto.X509StoreContext method),
        18
VERIFY_FAIL_IF_NO_PEER_CERT
                                        module
        OpenSSL.SSL), 26
VERIFY_NONE (in module OpenSSL.SSL), 26
VERIFY_PEER (in module OpenSSL.SSL), 26
W
want read() (OpenSSL.SSL.Connection method), 40
want_write() (OpenSSL.SSL.Connection method),
       40
WantReadError, 28
WantWriteError, 28
WantX509LookupError, 28
write() (OpenSSL.SSL.Connection method), 40
X
```

X509 (class in OpenSSL.crypto), 10